

The Four Steps to Deconstructing Multiples

Define the multiple

In use, the same multiple can be defined in different ways by different users. When comparing and using multiples, estimated by someone else, it is critical that we understand how the multiples have been estimated

Describe the multiple

Too many people who use a multiple have no idea what its cross sectional distribution is. If you do not know what the cross sectional distribution of a multiple is, it is difficult to look at a number and pass judgment on whether it is too high or low.

Analyze the multiple

It is critical that we understand the fundamentals that drive each multiple, and the nature of the relationship between the multiple and each variable.

Apply the multiple

Defining the comparable universe and controlling for differences is far more difficult in practice than it is in theory.

Definitional Tests

- □ Is the multiple consistently defined?
 - Proposition 1: Both the value (the numerator) and the standardizing variable (the denominator) should be to the same claimholders in the firm. In other words, the value of equity should be divided by equity earnings or equity book value, and firm value should be divided by firm earnings or book value.
- Is the multiple uniformly estimated?
 - The variables used in defining the multiple should be estimated uniformly across assets in the "comparable firm" list.
 - If earnings-based multiples are used, the accounting rules to measure earnings should be applied consistently across assets. The same rule applies with book-value based multiples.

Example 1: Price Earnings Ratio: Definition

PE = Market Price per Share / Earnings per Share

There are a number of variants on the basic PE ratio in use. They are based upon how the price and the earnings are defined.

Price: is usually the current price

is sometimes the average price for the year

EPS: EPS in most recent financial year

EPS in trailing 12 months

Forecasted earnings per share next year

Forecasted earnings per share in future year

Example 2: Staying on PE ratios

- Assuming that you are comparing the PE ratios across technology companies, many of which have options outstanding. What measure of PE ratio would yield the most consistent comparisons?
 - a. Price/ Primary EPS (actual shares, no options)
 - b. Price/ Fully Diluted EPS (actual shares + all options)
 - c. Price/ Partially Diluted EPS (counting only in-the-money options)
 - d. Other

Example 3: Enterprise Value / EBITDA Multiple

The enterprise value to EBITDA multiple is obtained by netting cash out against debt to arrive at enterprise value and dividing by EBITDA.

 $\frac{\text{Enterprise Value}}{\text{EBITDA}} = \frac{\text{Market Value of Equity + Market Value of Debt - Cash}}{\text{Earnings before Interest, Taxes and Depreciation}}$

- Why do we net out cash from firm value?
- 2. What happens if a firm has cross holdings which are categorized as:
 - Minority interests?
 - Majority active interests?

Example 4: A Housing Price Multiple


The bubbles and busts in housing prices has led investors to search for a multiple that they can use to determine when housing prices are getting out of line. One measure that has acquired adherents is the ratio of housing price to annual net rental income (for renting out the same house). Assume that you decide to compute this ratio and compare it to the multiple at which stocks are trading. Which valuation ratio would be the one that corresponds to the house price/rent ratio?

- a. Price Earnings Ratio
- b.EV to Sales
- c.EV to EBITDA
- d.EV to EBIT

Descriptive Tests

- What is the average and standard deviation for this multiple, across the universe (market)?
- What is the median for this multiple?
 - □ The median for this multiple is often a more reliable comparison point.
- How large are the outliers to the distribution, and how do we deal with the outliers?
 - Throwing out the outliers may seem like an obvious solution, but if the outliers all lie on one side of the distribution (they usually are large positive numbers), this can lead to a biased estimate.
- Are there cases where the multiple cannot be estimated? Will ignoring these cases lead to a biased estimate of the multiple?
- How has this multiple changed over time?

1. Multiples have skewed distributions... US company PE Ratios




2. Making statistics "dicey"

	Current PE	Trailing PE	Forward PE
Total Number of firms	7584	7584	7584
Firms with PE	2780	2481	2354
Average	109.79	103.25	79.74
Median	18.15	20.30	18.89
10th Percentile	6.95	7.68	8.96
First Quartile	10.41	11.50	12.36
Third Quartile	37.26	40.79	33.20
90th Percentile	95.44	96.80	69.40
Maximum	36157.14	25020.00	42390.00


US firms in January 2021

3. Markets have a lot in common: Comparing Global PEs







3a. And the differences are sometimes revealing... Price to Book Ratios across globe – January 2013



4. Simplistic rules almost always break down...6 times EBITDA was not cheap in 2010...



But it may be in 2021, unless you in Japan or Russia...



Analytical Tests

- What are the fundamentals that determine and drive these multiples?
 - Proposition 2: Embedded in every multiple are all of the variables that drive every discounted cash flow valuation - growth, risk and cash flow patterns.
- How do changes in these fundamentals change the multiple?
 - The relationship between a fundamental (like growth) and a multiple (such as PE) is almost never linear.
 - Proposition 3: It is impossible to properly compare firms on a multiple, if we do not know how fundamentals and the multiple move.

Start with a basic intrinsic value model Divide both sides of the equation by the denominator of the multiple that you are trying to deconstruct.

You should end up with an intrinsic version of your multiple, which should relate it to fundamentals.

If Equity Multiple

Start with a dividend or FCFE model, preferably simple.

Price= EPS * Payout / (r -g)

Divide your dividend or FCFE model by denominator of equity multiple.

Prtce/Book = ROE * Payout / (r -g)

Intrinsic version of equity multiple, with drivers of value

Price/Book = f(ROE, r, g, Payout)

If EV Multiple

Start with a operating asset value model, preferably simple.

> EV= EBIT (1-t) (1- RIR)/ (WACC -g)

Divide your operating asset model by denominator of EV multiple.

EV/Sales = After-tax Operating Margin (1- RIR)/ (WACC -g) Intrinsic version of EV multiple, with drivers of value

EV/Sales = f(After-tax Operating Margin, RIR, WACC, g)

I. PE Ratios

- To understand the fundamentals, start with a basic equity discounted cash flow model.
 - With the dividend discount model,

$$P_0 = \frac{DPS_1}{r - g_n}$$

Dividing both sides by the current earnings per share,

$$\frac{P_0}{EPS_0} = PE = \frac{Payout Ratio*(1+g_n)}{r-g_n}$$

If this had been a FCFE Model,

$$P_0 = \frac{\text{FCFE}_1}{r - g_n}$$

$$\frac{P_0}{\text{EPS}_0} = \text{PE} = \frac{(\text{FCFE/Earnings})*(1 + g_n)}{r - g_n}$$

Using the Fundamental Model to Estimate PE For a High Growth Firm

The price-earnings ratio for a high growth firm can also be related to fundamentals. In the special case of the two-stage dividend discount model, this relationship can be made explicit fairly simply:

$$P_{0} = \frac{EPS_{0}*Payout Ratio*(1+g)*\left(1 - \frac{(1+g)^{n}}{(1+r)^{n}}\right)}{r-g} + \frac{EPS_{0}*Payout Ratio_{n}*(1+g)^{n}*(1+g_{n})}{(r-g_{n})(1+r)^{n}}$$

- For a firm that does not pay what it can afford to in dividends, substitute FCFE/Earnings for the payout ratio.
- Dividing both sides by the earnings per share:

$$\frac{P_0}{EPS_0} = \frac{Payout Ratio * (1+g) * \left(1 - \frac{(1+g)^n}{(1+r)^n}\right)}{r - g} + \frac{Payout Ratio_n * (1+g)^n * (1+g_n)}{(r - g_n)(1+r)^n}$$

A Simple Example

 Assume that you have been asked to estimate the PE ratio for a firm which has the following characteristics:

Variable	High Growth Phase	Stable Growth Phase
Expected Growth Rate	25%	8%
Payout Ratio	20%	50%
Beta	1.00	1.00
Number of years	5 years	Forever after year 5


Riskfree rate = T.Bond Rate = 6%

Required rate of return = 6% + 1(5.5%) = 11.5%

$$\frac{P_0}{EPS_0} = \frac{.20*(1.25)*\left(1 - \frac{(1.25)^5}{(1.115)^5}\right)}{.115 - .25} + \frac{.50*(1.25)^5*(1.08)}{(.115 - .08)(1.115)^5} = 28.75$$


a. PE and Growth: Firm grows at x% for 5 years,8% thereafter

PE Ratios and Expected Growth: Interest Rate Scenarios




b. PE and Risk: A Follow up Example

PE Ratios and Beta: Growth Scenarios



Example 1: Comparing PE ratios across Emerging Markets- March 2014 (pre- Ukraine)



Source: Datastream, IBES, UBS GEMs Strategy

Example 2: An Old Example with Emerging Markets: June 2000

Country	PE Ratio	Interest	GDP Real	Country
		Rates	Growth	Risk
Argentina	14	18.00%	2.50%	45
Brazil	21	14.00%	4.80%	35
Chile	25	9.50%	5.50%	15
Hong Kong	20	8.00%	6.00%	15
India	17	11.48%	4.20%	25
Indonesia	15	21.00%	4.00%	50
Malaysia	14	5.67%	3.00%	40
Mexico	19	11.50%	5.50%	30
Pakistan	14	19.00%	3.00%	45
Peru	15	18.00%	4.90%	50
Phillipines	15	17.00%	3.80%	45
Singapore	24	6.50%	5.20%	5
South Korea	21	10.00%	4.80%	25
Thailand	21	12.75%	5.50%	25
Turkey	12	25.00%	2.00%	35
Venezuela	20	15.00%	3.50%	45

Regression Results

 The regression of PE ratios on these variables provides the following –

PE = 16.16

- 7.94 Interest Rates

+ 154.40 Growth in GDP

- 0.1116 Country Risk


R Squared = 73%

What do the coefficients tell you about how each of these variables play into PE ratio differences across countries?


Predicted PE Ratios

Country	PE Ratio	Interest	GDP Real	Country	Predicted PE
		Rates	Growth	Risk	
Argentina	14	18.00%	2.50%	45	13.57
Brazil	21	14.00%	4.80%	35	18.55
Chile	25	9.50%	5.50%	15	22.22
Hong Kong	20	8.00%	6.00%	15	23.11
India	17	11.48%	4.20%	25	18.94
Indonesia	15	21.00%	4.00%	50	15.09
Malaysia	14	5.67%	3.00%	40	15.87
Mexico	19	11.50%	5.50%	30	20.39
Pakistan	14	19.00%	3.00%	45	14.26
Peru	15	18.00%	4.90%	50	16.71
Phillipines	15	17.00%	3.80%	45	15.65
Singapore	24	6.50%	5.20%	5	23.11
South Korea	21	10.00%	4.80%	25	19.98
Thailand	21	12.75%	5.50%	25	20.85
Turkey	12	25.00%	2.00%	35	13.35
Venezuela	20	15.00%	3.50%	45	15.35


Example 3: US Stocks are expensive, just look at the PE ratio



A Counter: No, they are cheap, relative to the alternatives..



The Tie Breaker: E/P Ratios, T.Bond Rates and Term Structure



Regression Results

	Earnings Yield	T.Bond Rate	Bond-Bill
Earnings Yield	1.0000	10	
T.Bond Rate	0.6788	1.0000	
Bond-Bill	-0.1184	-0.0630	1.0000

Correlation between E/P and interest rates

In the following regression, using 1960-2020 data, we regress E/P ratios against the level of T.Bond rates and a term structure variable (T.Bond - T.Bill rate)

EP Ratio =
$$0.0359 + 0.5534$$
 T.Bond Rate - 0.1559 (T.Bond Rate - T.Bill Rate) (6.17) (7.01) (-0.79)

R squared = 44.81%

Going back to 2008, this is what the regression looked like:

$$E/P = 2.56\% + 0.7044$$
 T.Bond Rate $- 0.3289$ (T.Bond Rate-T.Bill Rate) (4.71) (7.10) (1.46)

R squared = 50.71%

The R-squared has dropped and the differential with the T.Bill rate has lost significance. How would you read this result?